

Sempertex\*

# Princess Birthday Hoop



Everyday Birthday

Designed By Chris Horne

## Product Required:

2 each of Sempertex 260 Satin Pink 20002848,  
Green 20002852, Blue 20002855 & Lilac 20002856.

1 each of Sempertex 260 Reflex Violet 20014188,  
Silver 20014184 and Pink 20014178

2 each of Sempertex 160 Satin Pink 20002751,  
Blue 20002763 and Lilac 20002764

3 x Sempertex 260 Reflex Gold 20014180

6 x Sempertex 160 Satin Green 20002762

Approx. 36 x Sempertex 5" Fashion White 20001968

6 x Sempertex 5" Pastel Matte Yellow 20012362

1 x Anagram Crystal Clearz Petite Light Pink 8298711

1 pack Amscan Mystical Fan Decorations 9909082

1 hoop frame, 80cm diameter

Balloon Bond or Glue Dots

Spare 260 balloons for tying in.



Estimated Labour time: 60 minutes.

## Construction Method:

1. Inflate 1 each of the Pastel Satin 260 Balloons fully, let a little air out to soften, then tie into a cluster of 4.
2. Wrap the cluster around the frame at the bottom left, then spiral the balloons around the frame until you almost reach the top. Tie off and secure.
3. Repeat with another 4 pastel satin 260 balloons, continuing the spiral until you reach the top right. Tie off and secure.
4. Inflate 4 of the satin green 160 balloons, tie into a cluster of 4 and wrap onto the frame at the bottom right.
5. Spiral the balloons around the frame until you meet the pastel 260s coming from the opposite direction. Tie off and secure.
6. Create 2 x Organic "clouds" with the 5" Fashion White balloons and wrap them onto the frame as shown.
7. Using the Lilac and Pink Reflex 260 balloons and one of the Satin Green 160 balloons, make a butterfly to cover the join between the two 260 spirals. Attach with Balloon Bond or glue dots.
8. Inflate the remaining 160 Satin Green balloon fully and wrap it loosely around the green spiral in the opposite direction. Decorate with small flowers made from the pink, lilac and blue satin 160s, and the 5" Pastel Matte Yellow balloons. Attach with balloon bond or Glue dots.
9. Create a small crown from the Silver, and 2 of the Gold, Reflex 260 Balloons.
10. Cut off the top of the Crystal Clearz Petites balloon, creating an opening about 4" wide. Carefully insert the crown, then re-seal the Clearz balloon with a heat sealer. A video tutorial on this technique can be found in the Decorator resources section of the Amscan UK website. Trim the seam as close to the new seal as possible, then inflate the Clearz balloon.
11. Inflate the last Reflex Gold 260 balloon fully, let a little air out, and wrap snugly around the Crystal Clearz balloon to cover the seam. Tie off securely and hold in place (if necessary) with Balloon Bond or glue dots.
12. Using an uninflated 260 balloon, Tie the Crystal Clearz balloon into the design as shown.
13. Assemble the three Paper fans and add to the design using balloon Bond or Glue dots as shown

our family of companies

